步驟流程圖:啟動 Conda 環境


步驟 1:確認 Conda 已安裝

請確認您已安裝 Anaconda 或 Miniconda。如果尚未安裝,可以前往以下連結下載 Miniconda:下載 Miniconda

步驟 2: 啟動 Conda

- 1. 開啟 Windows 的「開始」功能表。
- 2. 找到 Anaconda Prompt 或 Miniconda Prompt。
- 3. 點擊啟動對應的命令提示符環境。

下圖為 Anaconda Prompt 的範例:



- 4. 開啟後會出現如下畫面:
 - 畫面前綴顯示 (base),這代表目前正在 Conda 的虛擬環境中。

下圖為啟動後的畫面:



步驟 3:退出 base 環境

1. 在目前的命令提示符中輸入以下指令, 退出 base 虛擬環境(如果前面沒有虛擬環境就不用做這一步驟):

conda deactivate

結果會如下圖:



步驟 4: 切換至程式檔案資料夾

1. 請確認下載整個程式檔案資料夾·而不是單獨下載某個程式檔案。下載後·不需要更動資料夾中的內容。


2. 在 Conda Prompt 中,將當前工作路徑切換至程式檔案所在的資料夾。例如: 如果程式檔案資料夾的路徑是 C:\Users\Hoolu\Desktop\google_earth_engine_notebook,請在命令提示符中輸入:

cd C:\Users\Hoolu\Desktop\google_earth_engine_notebook



資料夾路徑如下圖:

在conda prompt下完指令後的結果:



步驟 5:建立 Google Earth Engine 的 Conda 虛擬環境

1. 在程式資料夾路徑下,輸入以下指令來建立專屬於 Google Earth Engine 的 Conda 虛擬環境

conda create -n google_earth_engine python=3.10

- 2. 請注意·Python 環境需求為 3.10 或以上,否則會無法正常運行。
- 3. 執行後,系統會出現安裝提示,直接輸入 y 進行確認。

下圖為執行指令和確認的範例畫面:

Anaconda Prompt - conda create -n google_earth_engine python=3.10

```
(base) C:\Users\Hoolu>conda deactivate
C:\Users\Hoolu>cd C:\Users\Hoolu\Desktop\google earth engine notebook
 :\Users\Hoolu\Desktop\google_earth_engine_notebook>conda create -n google_earth_engine python=3.10
Channels:
- defaults
Platform: win-64
Collecting package metadata (repodata.json): done
Solving environment: done
## Package Plan ##
   environment location: D:\miniconda3\envs\google_earth_engine
   added / updated specs:
       - python=3.10
The following NEW packages will be INSTALLED:
                                       pkgs/main/win-64::bzip2-1.0.8-h2bbff1b_6
pkgs/main/win-64::ca-certificates-2024.12.31-haa95532_0
pkgs/main/win-64::libffi-3.4.4-hd77b12b_1
pkgs/main/win-64::openss1-3.0.15-h827c3e9_0
pkgs/main/win-64::pip-24.2-py310haa95532_0
pkgs/main/win-64::python-3.10.16-h4607a30_1
pkgs/main/win-64::setuptools-75.1.0-py310haa95532_0
pkgs/main/win-64::sqlite-3.45.3-h2bbff1b_0
pkgs/main/win-64::tk-8.6.14-h0416ee5_0
pkgs/main/win-64::tzdata-2024b-h04d1e81_0
pkgs/main/win-64::vs2015_runtime-14.42.34433-h9531ae6_2
pkgs/main/win-64::vs2015_runtime-14.42.34433-h9531ae6_2
pkgs/main/win-64::xz-5.4.6-h8cc25b3_1
pkgs/main/win-64::zlib-1.2.13-h8cc25b3_1
                                       pkgs/main/win-64::bzip2-1.0.8-h2bbff1b_6
   bzip2
   ca-certificates
   libffi
   openssl
   pip
python
   setuptools
   sqlite
   tk
   tzdata
   vs2015_runtime
   wheel
   xz
zlib
Proceed ([y]/n)?
```

執行完成的書面:

🖏 選取 Anaconda Prompt

```
(base) C:\Users\Hoolu>conda deactivate
C:\Users\Hoolu>cd C:\Users\Hoolu\Desktop\google_earth_engine_notebook
  :\Users\Hoolu\Desktop\google_earth_engine_notebook>conda create -n google_earth_engine python=3.10
Channels:
- defaults
 Platform: win-64
Collecting package metadata (repodata.json): done
Solving environment: done
## Package Plan ##
   environment location: D:\miniconda3\envs\google_earth_engine
   added / updated specs:
       - python=3.10
The following NEW packages will be INSTALLED:
                                      pkgs/main/win-64::bzip2-1.0.8-h2bbff1b_6
pkgs/main/win-64::ca-certificates-2024.12.31-haa95532_0
pkgs/main/win-64::libffi-3.4.4-hd77b12b_1
pkgs/main/win-64::openss1-3.0.15-h827c3e9_0
pkgs/main/win-64::pyip-24.2-py310haa95532_0
pkgs/main/win-64::python-3.10.16-h4607a30_1
pkgs/main/win-64::setuptools-75.1.0-py310haa95532_0
pkgs/main/win-64::sqlite-3.45.3-h2bbff1b_0
pkgs/main/win-64::tk-8.6.14-h0416ee5_0
pkgs/main/win-64::tzdata-2024b-h04d1e81_0
pkgs/main/win-64::vc-14.40-haa95532_2
pkgs/main/win-64::vs2015_runtime-14.42.34433-h9531ae6_2
pkgs/main/win-64::vs20.44.0-py310haa95532_0
pkgs/main/win-64::vs2.5.4.6-h8cc25b3_1
pkgs/main/win-64::zlib-1.2.13-h8cc25b3_1
   ca-certificates
libffi
   openssl
   pip
python
   setuptools
sqlite
tk
   tzdata
   vc
vs2015_runtime
   wheel
   xz
zlib
Proceed ([y]/n)? y
Downloading and Extracting Packages:
Preparing transaction: done
Verifying transaction: done
Executing transaction: done
   To activate this environment, use
           $ conda activate google_earth_engine
   To deactivate an active environment, use
           $ conda deactivate
C:\Users\Hoolu\Desktop\google_earth_engine_notebook>
```

步驟 6:進入 Google Earth Engine 的 Conda 虛擬環境 & 安裝相關套件

1. 在conda prompt下進入虛擬環境的指令即可**conda activate <虛擬環境名稱>

```
conda activate google_earth_engine
```

結果如下圖:

```
Downloading and Extracting Packages:

Preparing transaction: done
Verifying transaction: done
Executing transaction: done

#
# To activate this environment, use
#
# $ conda activate google_earth_engine
#
# To deactivate an active environment, use
#
# $ conda deactivate

C:\Users\Hoolu\Desktop\google_earth_engine_notebook>conda activate google_earth_engine

(google_earth_engine) C:\Users\Hoolu\Desktop\google_earth_engine_notebook>
```

看到前面出現了虛擬環境名稱就代表成功進入了

2. 安裝相關套件,已經把需要的套件都寫在requirements.txt裡面了,所以只需要把**pip install packages指定到文字檔上即可,請不要自己亂安裝避免套件衝突

```
pip install -r requirements.txt
```

```
C:\Users\Hoolu\Desktop\google_earth_engine_notebook>conda activate google_earth_engine

(google_earth_engine) C:\Users\Hoolu\Desktop\google_earth_engine_notebook>pip install -r requirements.txt

Collecting geemap=0.32.0 (from -r requirements.txt (line 1))

Using cached geemap-0.32.0-py2.py3-none-any.whl.metadata (14 kB)

Collecting tk=0.1.0 (from -r requirements.txt (line 2))

Using cached tk-0.1.0-py3-none-any.whl.metadata (693 bytes)

Collecting ipykernel=6.29.5 (from -r requirements.txt (line 3))

Downloading ipykernel-6.29.5-py3-none-any.whl.metadata (6.3 kB)

Collecting bqplot (from geemap=0.32.0->-r requirements.txt (line 1))

Downloading bqplot-0.12.44-py2.py3-none-any.whl.metadata (6.4 kB)

Collecting colour (from geemap=0.32.0->-r requirements.txt (line 1))

Using cached colour-0.1.5-py2.py3-none-any.whl.metadata (18 kB)

Collecting earthengine-api=0.1.347 (from geemap=0.32.0->-r requirements.txt (line 1))

Downloading earthengine-api=1.4.5-py3-none-any.whl.metadata (1.8 kB)

Collecting eerepr=0.0.4 (from geemap=0.32.0->-r requirements.txt (line 1))

Downloading eerepr-0.1.0-py3-none-any.whl.metadata (4.3 kB)

Collecting folium>0.13.0 (from geemap=0.32.0->-r requirements.txt (line 1))

Downloading folium>0.13.0 (from geemap=0.32.0->-r requirements.txt (line 1))

Using cached geocoder (from geemap=0.32.0->-r requirements.txt (line 1))

Using cached geocoder-1.38.1-py2.py3-none-any.whl.metadata (14 kB)

Collecting invocate (from geemap=0.32.0->-r requirements.txt (line 1))
```

3. 安裝完後會看到下圖:

```
l (70 kB)
.py3-none-any.whl (214 kB)
kl0-win_and64.whl (15 kB)
any.whl (103 kB)
cone-any.whl (181 kB)
                                                                                                                                                                                                                                                                                                                                                                                                                                                  5.0,5-25,10mg - 25,20mg - 
ind rea-4-2) read 1. 1. 270 ready shift to the read
```

4. 安裝Jupyter Notebook,Conda可以直接用他自己的辦法安裝Jupyter Notebook · 所以直接下指令:

```
conda install jupyter
```

這邊依樣直接按y

```
Proceed ([y]/n)?
```

安裝完後會如下圖,可以直接下指令即可啟動:


Jupyter Notebook

Anaconda Prompt - conda activate google_earth_engine - conda install jupyter

done

(google_earth_engine) C:\Users\Hoolu\Desktop\google_earth_engine_notebook>Jupyter Notebook

啟動後就會直接跳出程式資料夾,這樣就完成了:



註:之後的啟動方式

未來再打開conda prompt後發現虛擬環境不是google earth engine的環境,可以善用**conda deactivate**來退出當前環境,之後再用**conda activate <google earth engine虛擬環境名稱>來進入到之前建立的google earth engine虛擬環境。

退出當前虛擬環境語法
conda deactivate

進入虛擬環境語法
conda activate <虛擬環境名稱>

查看虛擬環境清單
conda env list